

primesieve

7.0

Generated by Doxygen 1.8.13



# Contents

<b>1</b>	<b>Main Page</b>	<b>1</b>
1.1	About . . . . .	1
1.2	C++ API . . . . .	1
1.3	C API . . . . .	1
<b>2</b>	<b>Namespace Index</b>	<b>3</b>
2.1	Namespace List . . . . .	3
<b>3</b>	<b>Hierarchical Index</b>	<b>5</b>
3.1	Class Hierarchy . . . . .	5
<b>4</b>	<b>Class Index</b>	<b>7</b>
4.1	Class List . . . . .	7
<b>5</b>	<b>File Index</b>	<b>9</b>
5.1	File List . . . . .	9
<b>6</b>	<b>Namespace Documentation</b>	<b>11</b>
6.1	primesieve Namespace Reference . . . . .	11
6.1.1	Detailed Description . . . . .	12
6.1.2	Function Documentation . . . . .	12
6.1.2.1	count_primes() . . . . .	12
6.1.2.2	count_quadruplets() . . . . .	13
6.1.2.3	count_quintuplets() . . . . .	13
6.1.2.4	count_sextuplets() . . . . .	13
6.1.2.5	count_triplets() . . . . .	13
6.1.2.6	count_twins() . . . . .	13
6.1.2.7	get_max_stop() . . . . .	14
6.1.2.8	nth_prime() . . . . .	14
6.1.2.9	set_num_threads() . . . . .	14
6.1.2.10	set_sieve_size() . . . . .	14

<b>7</b>	<b>Class Documentation</b>	<b>17</b>
7.1	primesieve::iterator Class Reference . . . . .	17
7.1.1	Detailed Description . . . . .	17
7.1.2	Constructor & Destructor Documentation . . . . .	17
7.1.2.1	iterator() . . . . .	17
7.1.3	Member Function Documentation . . . . .	18
7.1.3.1	next_prime() . . . . .	18
7.1.3.2	prev_prime() . . . . .	18
7.1.3.3	skipto() . . . . .	18
7.2	primesieve::primesieve_error Class Reference . . . . .	19
7.2.1	Detailed Description . . . . .	20
7.3	primesieve_iterator Struct Reference . . . . .	20
7.3.1	Detailed Description . . . . .	20
<b>8</b>	<b>File Documentation</b>	<b>21</b>
8.1	iterator.h File Reference . . . . .	21
8.1.1	Detailed Description . . . . .	22
8.1.2	Function Documentation . . . . .	22
8.1.2.1	primesieve_next_prime() . . . . .	22
8.1.2.2	primesieve_prev_prime() . . . . .	23
8.1.2.3	primesieve_skipto() . . . . .	23
8.2	iterator.hpp File Reference . . . . .	23
8.2.1	Detailed Description . . . . .	25
8.3	primesieve.h File Reference . . . . .	25
8.3.1	Detailed Description . . . . .	27
8.3.2	Enumeration Type Documentation . . . . .	27
8.3.2.1	anonymous enum . . . . .	27
8.3.3	Function Documentation . . . . .	27
8.3.3.1	primesieve_count_primes() . . . . .	27
8.3.3.2	primesieve_count_quadruplets() . . . . .	28
8.3.3.3	primesieve_count_quintuplets() . . . . .	28

8.3.3.4	<code>primesieve_count_sextuplets()</code>	28
8.3.3.5	<code>primesieve_count_triplets()</code>	28
8.3.3.6	<code>primesieve_count_twins()</code>	29
8.3.3.7	<code>primesieve_generate_n_primes()</code>	29
8.3.3.8	<code>primesieve_generate_primes()</code>	29
8.3.3.9	<code>primesieve_get_max_stop()</code>	30
8.3.3.10	<code>primesieve_nth_prime()</code>	30
8.3.3.11	<code>primesieve_set_num_threads()</code>	30
8.3.3.12	<code>primesieve_set_sieve_size()</code>	30
8.4	<code>primesieve.hpp</code> File Reference	31
8.4.1	Detailed Description	33
8.5	<code>primesieve_error.hpp</code> File Reference	33
8.5.1	Detailed Description	34
<b>9</b>	<b>Example Documentation</b>	<b>35</b>
9.1	<code>count_primes.c</code>	35
9.2	<code>count_primes.cpp</code>	35
9.3	<code>nth_prime.c</code>	35
9.4	<code>nth_prime.cpp</code>	36
9.5	<code>prev_prime.c</code>	36
9.6	<code>prev_prime.cpp</code>	37
9.7	<code>primesieve_iterator.c</code>	37
9.8	<code>primesieve_iterator.cpp</code>	37
9.9	<code>store_primes_in_array.c</code>	38
9.10	<code>store_primes_in_vector.cpp</code>	38
	<b>Index</b>	<b>41</b>



# Chapter 1

## Main Page

### 1.1 About

primesieve is a C/C++ library for fast prime number generation. It generates the primes below  $10^9$  in just 0.2 seconds on a single core of an Intel Core i7-6700 3.4GHz CPU. primesieve can generate primes and prime k-tuplets up to  $2^{64}$ . primesieve's memory requirement is about  $\pi(\sqrt{n}) * 8$  bytes per thread, its run-time complexity is  $O(n \log \log n)$  operations. The recommended way to get started is to first have a look at a few C or C++ example programs. The most common use cases are iterating over primes using `next_prime()` or `prev_prime()` and storing primes in a vector or an array.

For more information please visit <https://primesieve.org>.

### 1.2 C++ API

- [primesieve.hpp](#) - primesieve C++ header.
- [primesieve\\_iterator.cpp](#) - Example that shows how to iterate over primes using `primesieve::iterator`.
- [store\\_primes\\_in\\_vector.cpp](#) - Example that shows how to store primes in a `std::vector`.
- [count\\_primes.cpp](#) - Example that shows how to count primes.

### 1.3 C API

- [primesieve.h](#) - primesieve C header.
- [primesieve\\_iterator.c](#) - Example that shows how to iterate over primes using `primesieve_iterator`.
- [store\\_primes\\_in\\_array.c](#) - Example that shows how to store primes in an array.
- [count\\_primes.c](#) - Example that shows how to count primes.





## Chapter 2

# Namespace Index

### 2.1 Namespace List

Here is a list of all documented namespaces with brief descriptions:

<a href="#">primesieve</a>	
Contains primesieve's C++ functions and classes . . . . .	<a href="#">11</a>



## Chapter 3

# Hierarchical Index

### 3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

primesieve::iterator . . . . .	17
primesieve_iterator . . . . .	20
runtime_error	
primesieve::primesieve_error . . . . .	19



## Chapter 4

# Class Index

### 4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

<a href="#">primesieve::iterator</a>	Primesieve::iterator allows to easily iterate over primes both forwards and backwards . . . . .	17
<a href="#">primesieve::primesieve_error</a>	Primesieve throws a <a href="#">primesieve_error</a> exception if an error occurs e.g . . . . .	19
<a href="#">primesieve_iterator</a>	C prime iterator, please refer to <a href="#">iterator.h</a> for more information . . . . .	20



## Chapter 5

# File Index

### 5.1 File List

Here is a list of all documented files with brief descriptions:

<a href="#">iterator.h</a>	Primesieve_iterator allows to easily iterate over primes both forwards and backwards . . . . .	21
<a href="#">iterator.hpp</a>	The iterator class allows to easily iterate (forwards and backwards) over prime numbers . . . . .	23
<a href="#">primesieve.h</a>	Primesieve C API . . . . .	25
<a href="#">primesieve.hpp</a>	Primesieve C++ API . . . . .	31
<a href="#">primesieve_error.hpp</a>	The primesieve_error class is used for all exceptions within primesieve . . . . .	33





## Chapter 6

# Namespace Documentation

### 6.1 primesieve Namespace Reference

Contains primesieve's C++ functions and classes.

#### Classes

- class [iterator](#)  
*[primesieve::iterator](#) allows to easily iterate over primes both forwards and backwards.*
- class [primesieve\\_error](#)  
*primesieve throws a [primesieve\\_error](#) exception if an error occurs e.g.*

#### Functions

- `template<typename T >`  
`void generate\_primes (uint64_t stop, std::vector< T > *primes)`  
*Store the primes  $\leq$  stop in the primes vector.*
- `template<typename T >`  
`void generate\_primes (uint64_t start, uint64_t stop, std::vector< T > *primes)`  
*Store the primes within the interval [start, stop] in the primes vector.*
- `template<typename T >`  
`void generate\_n\_primes (uint64_t n, std::vector< T > *primes)`  
*Store the first n primes in the primes vector.*
- `template<typename T >`  
`void generate\_n\_primes (uint64_t n, uint64_t start, std::vector< T > *primes)`  
*Store the first n primes  $\geq$  start in the primes vector.*
- `uint64_t nth\_prime (int64_t n, uint64_t start=0)`  
*Find the nth prime.*
- `uint64_t count\_primes (uint64_t start, uint64_t stop)`  
*Count the primes within the interval [start, stop].*
- `uint64_t count\_twins (uint64_t start, uint64_t stop)`  
*Count the twin primes within the interval [start, stop].*
- `uint64_t count\_triplets (uint64_t start, uint64_t stop)`  
*Count the prime triplets within the interval [start, stop].*
- `uint64_t count\_quadruplets (uint64_t start, uint64_t stop)`

- Count the prime quadruplets within the interval [start, stop].*
- uint64\_t [count\\_quintuplets](#) (uint64\_t start, uint64\_t stop)
- Count the prime quintuplets within the interval [start, stop].*
- uint64\_t [count\\_sextuplets](#) (uint64\_t start, uint64\_t stop)
- Count the prime sextuplets within the interval [start, stop].*
- void [print\\_primes](#) (uint64\_t start, uint64\_t stop)
- Print the primes within the interval [start, stop] to the standard output.*
- void [print\\_twins](#) (uint64\_t start, uint64\_t stop)
- Print the twin primes within the interval [start, stop] to the standard output.*
- void [print\\_triplets](#) (uint64\_t start, uint64\_t stop)
- Print the prime triplets within the interval [start, stop] to the standard output.*
- void [print\\_quadruplets](#) (uint64\_t start, uint64\_t stop)
- Print the prime quadruplets within the interval [start, stop] to the standard output.*
- void [print\\_quintuplets](#) (uint64\_t start, uint64\_t stop)
- Print the prime quintuplets within the interval [start, stop] to the standard output.*
- void [print\\_sextuplets](#) (uint64\_t start, uint64\_t stop)
- Print the prime sextuplets within the interval [start, stop] to the standard output.*
- uint64\_t [get\\_max\\_stop](#) ()
- Returns the largest valid stop number for primesieve.*
- int [get\\_sieve\\_size](#) ()
- Get the current set sieve size in kilobytes.*
- int [get\\_num\\_threads](#) ()
- Get the current set number of threads.*
- void [set\\_sieve\\_size](#) (int sieve\_size)
- Set the sieve size in kilobytes.*
- void [set\\_num\\_threads](#) (int num\_threads)
- Set the number of threads for use in primesieve::count\_\*() and [primesieve::nth\\_prime\(\)](#).*
- std::string [primesieve\\_version](#) ()
- Get the primesieve version number, in the form "i.j".*

### 6.1.1 Detailed Description

Contains primesieve's C++ functions and classes.

### 6.1.2 Function Documentation

#### 6.1.2.1 count\_primes()

```
uint64_t primesieve::count_primes (
    uint64_t start,
    uint64_t stop )
```

Count the primes within the interval [start, stop].

By default all CPU cores are used, use [primesieve::set\\_num\\_threads\(int threads\)](#) to change the number of threads.

Examples:

[count\\_primes.cpp](#).

#### 6.1.2.2 count\_quadruplets()

```
uint64_t primesieve::count_quadruplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime quadruplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve::set\\_num\\_threads\(int threads\)](#) to change the number of threads.

#### 6.1.2.3 count\_quintuplets()

```
uint64_t primesieve::count_quintuplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime quintuplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve::set\\_num\\_threads\(int threads\)](#) to change the number of threads.

#### 6.1.2.4 count\_sextuplets()

```
uint64_t primesieve::count_sextuplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime sextuplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve::set\\_num\\_threads\(int threads\)](#) to change the number of threads.

#### 6.1.2.5 count\_triplets()

```
uint64_t primesieve::count_triplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime triplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve::set\\_num\\_threads\(int threads\)](#) to change the number of threads.

#### 6.1.2.6 count\_twins()

```
uint64_t primesieve::count_twins (
    uint64_t start,
    uint64_t stop )
```

Count the twin primes within the interval [start, stop].

By default all CPU cores are used, use [primesieve::set\\_num\\_threads\(int threads\)](#) to change the number of threads.

### 6.1.2.7 `get_max_stop()`

```
uint64_t primesieve::get_max_stop ( )
```

Returns the largest valid stop number for primesieve.

#### Returns

$2^{64}-1$  (UINT64\_MAX).

### 6.1.2.8 `nth_prime()`

```
uint64_t primesieve::nth_prime (
    int64_t n,
    uint64_t start = 0 )
```

Find the nth prime.

By default all CPU cores are used, use [primesieve::set\\_num\\_threads\(int threads\)](#) to change the number of threads.

#### Parameters

<i>n</i>	if $n = 0$ finds the 1st prime $\geq$ start, if $n > 0$ finds the nth prime $>$ start, if $n < 0$ finds the nth prime $<$ start (backwards).
----------	--

#### Examples:

[nth\\_prime.cpp](#).

### 6.1.2.9 `set_num_threads()`

```
void primesieve::set_num_threads (
    int num_threads )
```

Set the number of threads for use in [primesieve::count\\_\\*](#)() and [primesieve::nth\\_prime\(\)](#).

By default all CPU cores are used.

### 6.1.2.10 `set_sieve_size()`

```
void primesieve::set_sieve_size (
    int sieve_size )
```

Set the sieve size in kilobytes.

The best sieving performance is achieved with a sieve size of your CPU's L1 or L2 cache size (per core).

## Parameters

<i>sieve_size</i>	Sieve size in kilobytes.
-------------------	--------------------------

## Precondition

`sieve_size >= 8 && <= 4096.`



## Chapter 7

# Class Documentation

### 7.1 primesieve::iterator Class Reference

[primesieve::iterator](#) allows to easily iterate over primes both forwards and backwards.

```
#include <iterator.hpp>
```

#### Public Member Functions

- [iterator](#) (uint64\_t start=0, uint64\_t stop\_hint=[get\\_max\\_stop](#)())  
*Create a new iterator object.*
- void [skipto](#) (uint64\_t start, uint64\_t stop\_hint=[get\\_max\\_stop](#)())  
*Reset the primesieve iterator to start.*
- uint64\_t [next\\_prime](#) ()  
*Get the next prime.*
- uint64\_t [prev\\_prime](#) ()  
*Get the previous prime.*

#### 7.1.1 Detailed Description

[primesieve::iterator](#) allows to easily iterate over primes both forwards and backwards.

Generating the first prime has a complexity of  $O(r \log \log r)$  operations with  $r = n^{0.5}$ , after that any additional prime is generated in amortized  $O(\log n \log \log n)$  operations. The memory usage is  $\text{PrimePi}(n^{0.5}) * 8$  bytes.

Examples:

[prev\\_prime.cpp](#), and [primesieve\\_iterator.cpp](#).

#### 7.1.2 Constructor & Destructor Documentation

##### 7.1.2.1 iterator()

```
primesieve::iterator::iterator (  
    uint64_t start = 0,  
    uint64_t stop_hint = get\_max\_stop() )
```

Create a new iterator object.

## Parameters

<i>start</i>	Generate primes $>$ start (or $<$ start).
<i>stop_hint</i>	Stop number optimization hint, gives significant speed up if few primes are generated. E.g. if you want to generate the primes below 1000 use <code>stop_hint = 1000</code> .

### 7.1.3 Member Function Documentation

#### 7.1.3.1 `next_prime()`

```
uint64_t primesieve::iterator::next_prime ( ) [inline]
```

Get the next prime.

Returns `UINT64_MAX` if next prime  $> 2^{64}$ .

Examples:

[primesieve\\_iterator.cpp](#).

#### 7.1.3.2 `prev_prime()`

```
uint64_t primesieve::iterator::prev_prime ( ) [inline]
```

Get the previous prime.

`prev_prime(n) = 0` if  $n \leq 2$ .

Examples:

[prev\\_prime.cpp](#).

#### 7.1.3.3 `skipto()`

```
void primesieve::iterator::skipto (
    uint64_t start,
    uint64_t stop_hint = get\_max\_stop\(\) )
```

Reset the primesieve iterator to start.



## Parameters

<i>start</i>	Generate primes > start (or < start).
<i>stop_hint</i>	Stop number optimization hint, gives significant speed up if few primes are generated. E.g. if you want to generate the primes below 1000 use stop_hint = 1000.

## Examples:

[prev\\_prime.cpp](#), and [primesieve\\_iterator.cpp](#).

The documentation for this class was generated from the following file:


- [iterator.hpp](#)

## 7.2 primesieve::primesieve\_error Class Reference


primesieve throws a [primesieve\\_error](#) exception if an error occurs e.g.

```
#include <primesieve_error.hpp>
```

Inheritance diagram for primesieve::primesieve\_error:



Collaboration diagram for primesieve::primesieve\_error:



## Public Member Functions

- **primesieve\_error** (const std::string &msg)

### 7.2.1 Detailed Description

primesieve throws a [primesieve\\_error](#) exception if an error occurs e.g.

prime > 2^64.

The documentation for this class was generated from the following file:

- [primesieve\\_error.hpp](#)

## 7.3 primesieve\_iterator Struct Reference

C prime iterator, please refer to [iterator.h](#) for more information.

```
#include <iterator.h>
```

## Public Attributes

- size\_t **i**
- size\_t **last\_idx**
- uint64\_t **start**
- uint64\_t **stop**
- uint64\_t **stop\_hint**
- uint64\_t **dist**
- uint64\_t \* **primes**
- void \* **vector**
- void \* **primeGenerator**
- int **is\_error**

### 7.3.1 Detailed Description

C prime iterator, please refer to [iterator.h](#) for more information.

Examples:

[prev\\_prime.c](#), and [primesieve\\_iterator.c](#).

The documentation for this struct was generated from the following file:

- [iterator.h](#)

## Chapter 8


# File Documentation

### 8.1 iterator.h File Reference


[primesieve\\_iterator](#) allows to easily iterate over primes both forwards and backwards.

```
#include <stdint.h>
#include <stddef.h>
```

Include dependency graph for iterator.h:



This graph shows which files directly or indirectly include this file:



## Classes

- struct [primesieve\\_iterator](#)  
C prime iterator, please refer to [iterator.h](#) for more information.

## Functions

- void [primesieve\\_init](#) ([primesieve\\_iterator](#) \*it)  
*Initialize the primesieve iterator before first using it.*
- void [primesieve\\_free\\_iterator](#) ([primesieve\\_iterator](#) \*it)  
*Free all memory.*
- void [primesieve\\_skipto](#) ([primesieve\\_iterator](#) \*it, uint64\_t start, uint64\_t stop\_hint)  
*Reset the primesieve iterator to start.*
- static uint64\_t [primesieve\\_next\\_prime](#) ([primesieve\\_iterator](#) \*it)  
*Get the next prime.*
- static uint64\_t [primesieve\\_prev\\_prime](#) ([primesieve\\_iterator](#) \*it)  
*Get the previous prime.*

### 8.1.1 Detailed Description

[primesieve\\_iterator](#) allows to easily iterate over primes both forwards and backwards.

Generating the first prime has a complexity of  $O(r \log \log r)$  operations with  $r = n^{0.5}$ , after that any additional prime is generated in amortized  $O(\log n \log \log n)$  operations. The memory usage is about  $\text{PrimePi}(n^{0.5}) * 8$  bytes.

The [primesieve\\_iterator.c](#) example shows how to use [primesieve\\_iterator](#). If any error occurs [primesieve\\_next\\_prime\(\)](#) and [primesieve\\_prev\\_prime\(\)](#) return `PRIMESIEVE_ERROR`. Furthermore `primesieve_iterator.is_error` is initialized to 0 and set to 1 if any error occurs.

Copyright (C) 2018 Kim Walisch, [kim.walisch@gmail.com](mailto:kim.walisch@gmail.com)

This file is distributed under the BSD License. See the COPYING file in the top level directory.

### 8.1.2 Function Documentation

#### 8.1.2.1 [primesieve\\_next\\_prime\(\)](#)

```
static uint64_t primesieve_next_prime (
    primesieve\_iterator * it )  [inline], [static]
```

Get the next prime.

Returns `UINT64_MAX` if next prime  $> 2^{64}$ .

Examples:

[primesieve\\_iterator.c](#).

## 8.1.2.2 primesieve\_prev\_prime()

```
static uint64_t primesieve_prev_prime (
    primesieve_iterator * it ) [inline], [static]
```

Get the previous prime.

primesieve\_prev\_prime(n) = 0 if n <= 2.

Examples:

[prev\\_prime.c](#).

## 8.1.2.3 primesieve\_skipto()

```
void primesieve_skipto (
    primesieve_iterator * it,
    uint64_t start,
    uint64_t stop_hint )
```

Reset the primesieve iterator to start.

Parameters

<i>start</i>	Generate primes > start (or < start).
<i>stop_hint</i>	Stop number optimization hint. E.g. if you want to generate the primes below 1000 use stop_hint = 1000, if you don't know use <a href="#">primesieve_get_max_stop()</a> .

Examples:


[prev\\_prime.c](#), and [primesieve\\_iterator.c](#).

## 8.2 iterator.hpp File Reference


The iterator class allows to easily iterate (forwards and backwards) over prime numbers.

```
#include <stdint.h>
#include <cstdint>
#include <vector>
#include <memory>
```

Include dependency graph for iterator.hpp:



This graph shows which files directly or indirectly include this file:



## Classes

- class [primesieve::iterator](#)  
*[primesieve::iterator](#) allows to easily iterate over primes both forwards and backwards.*

## Namespaces

- [primesieve](#)  
*Contains primesieve's C++ functions and classes.*

## Functions

- `uint64_t` [primesieve::get\\_max\\_stop\(\)](#)  
*Returns the largest valid stop number for primesieve.*

### 8.2.1 Detailed Description

The iterator class allows to easily iterate (forwards and backwards) over prime numbers.


Copyright (C) 2018 Kim Walisch, [kim.walisch@gmail.com](mailto:kim.walisch@gmail.com)

This file is distributed under the BSD License. See the COPYING file in the top level directory.

## 8.3 primesieve.h File Reference

primesieve C API.

```
#include <primesieve/iterator.h>
#include <stdint.h>
#include <stddef.h>
Include dependency graph for primesieve.h:
```



### Macros

- `#define PRIMESIEVE_VERSION "7.0"`
- `#define PRIMESIEVE_VERSION_MAJOR 7`
- `#define PRIMESIEVE_VERSION_MINOR 0`
- `#define PRIMESIEVE_ERROR ((uint64_t) ~((uint64_t) 0))`  
*primesieve functions return PRIMESIEVE\_ERROR (UINT64\_MAX) if any error occurs.*

### Enumerations

- `enum {`  
`SHORT_PRIMES, USHORT_PRIMES, INT_PRIMES, UINT_PRIMES,`  
`LONG_PRIMES, ULONG_PRIMES, LONGLONG_PRIMES, ULONGLONG_PRIMES,`  
`INT16_PRIMES, UINT16_PRIMES, INT32_PRIMES, UINT32_PRIMES,`  
`INT64_PRIMES, UINT64_PRIMES }`

## Functions

- void \* [primesieve\\_generate\\_primes](#) (uint64\_t start, uint64\_t stop, size\_t \*size, int type)  
*Get an array with the primes inside the interval [start, stop].*
- void \* [primesieve\\_generate\\_n\\_primes](#) (uint64\_t n, uint64\_t start, int type)  
*Get an array with the first n primes  $\geq$  start.*
- uint64\_t [primesieve\\_nth\\_prime](#) (int64\_t n, uint64\_t start)  
*Find the nth prime.*
- uint64\_t [primesieve\\_count\\_primes](#) (uint64\_t start, uint64\_t stop)  
*Count the primes within the interval [start, stop].*
- uint64\_t [primesieve\\_count\\_twins](#) (uint64\_t start, uint64\_t stop)  
*Count the twin primes within the interval [start, stop].*
- uint64\_t [primesieve\\_count\\_triplets](#) (uint64\_t start, uint64\_t stop)  
*Count the prime triplets within the interval [start, stop].*
- uint64\_t [primesieve\\_count\\_quadruplets](#) (uint64\_t start, uint64\_t stop)  
*Count the prime quadruplets within the interval [start, stop].*
- uint64\_t [primesieve\\_count\\_quintuplets](#) (uint64\_t start, uint64\_t stop)  
*Count the prime quintuplets within the interval [start, stop].*
- uint64\_t [primesieve\\_count\\_sextuplets](#) (uint64\_t start, uint64\_t stop)  
*Count the prime sextuplets within the interval [start, stop].*
- void [primesieve\\_print\\_primes](#) (uint64\_t start, uint64\_t stop)  
*Print the primes within the interval [start, stop] to the standard output.*
- void [primesieve\\_print\\_twins](#) (uint64\_t start, uint64\_t stop)  
*Print the twin primes within the interval [start, stop] to the standard output.*
- void [primesieve\\_print\\_triplets](#) (uint64\_t start, uint64\_t stop)  
*Print the prime triplets within the interval [start, stop] to the standard output.*
- void [primesieve\\_print\\_quadruplets](#) (uint64\_t start, uint64\_t stop)  
*Print the prime quadruplets within the interval [start, stop] to the standard output.*
- void [primesieve\\_print\\_quintuplets](#) (uint64\_t start, uint64\_t stop)  
*Print the prime quintuplets within the interval [start, stop] to the standard output.*
- void [primesieve\\_print\\_sextuplets](#) (uint64\_t start, uint64\_t stop)  
*Print the prime sextuplets within the interval [start, stop] to the standard output.*
- uint64\_t [primesieve\\_get\\_max\\_stop](#) ()  
*Returns the largest valid stop number for primesieve.*
- int [primesieve\\_get\\_sieve\\_size](#) ()  
*Get the current set sieve size in kilobytes.*
- int [primesieve\\_get\\_num\\_threads](#) ()  
*Get the current set number of threads.*
- void [primesieve\\_set\\_sieve\\_size](#) (int sieve\_size)  
*Set the sieve size in kilobytes.*
- void [primesieve\\_set\\_num\\_threads](#) (int num\_threads)  
*Set the number of threads for use in [primesieve\\_count\\_\\*\(\)](#) and [primesieve\\_nth\\_prime\(\)](#).*
- void [primesieve\\_free](#) (void \*primes)  
*Deallocate a primes array created using the [primesieve\\_generate\\_primes\(\)](#) or [primesieve\\_generate\\_n\\_primes\(\)](#) functions.*
- const char \* [primesieve\\_version](#) ()  
*Get the primesieve version number, in the form "i.j"*



### 8.3.1 Detailed Description

primesieve C API.

primesieve is a library for fast prime number generation. In case an error occurs `errno` is set to `EDOM` and `PRIMESIEVE_ERROR` is returned.

Copyright (C) 2018 Kim Walisch, [kim.walisch@gmail.com](mailto:kim.walisch@gmail.com)

This file is distributed under the BSD License.

### 8.3.2 Enumeration Type Documentation

#### 8.3.2.1 anonymous enum

anonymous enum

Enumerator

SHORT_PRIMES	Generate primes of short type.
USHORT_PRIMES	Generate primes of unsigned short type.
INT_PRIMES	Generate primes of int type.
UINT_PRIMES	Generate primes of unsigned int type.
LONG_PRIMES	Generate primes of long type.
ULONG_PRIMES	Generate primes of unsigned long type.
LONGLONG_PRIMES	Generate primes of long long type.
ULONGLONG_PRIMES	Generate primes of unsigned long long type.
INT16_PRIMES	Generate primes of int16_t type.
UINT16_PRIMES	Generate primes of uint16_t type.
INT32_PRIMES	Generate primes of int32_t type.
UINT32_PRIMES	Generate primes of uint32_t type.
INT64_PRIMES	Generate primes of int64_t type.
UINT64_PRIMES	Generate primes of uint64_t type.

### 8.3.3 Function Documentation

#### 8.3.3.1 primesieve\_count\_primes()

```
uint64_t primesieve_count_primes (
    uint64_t start,
    uint64_t stop )
```

Count the primes within the interval [start, stop].

By default all CPU cores are used, use [primesieve\\_set\\_num\\_threads\(int threads\)](#) to change the number of threads.

Examples:

[count\\_primes.c](#).

#### 8.3.3.2 primesieve\_count\_quadruplets()

```
uint64_t primesieve_count_quadruplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime quadruplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve\\_set\\_num\\_threads\(int threads\)](#) to change the number of threads.

#### 8.3.3.3 primesieve\_count\_quintuplets()

```
uint64_t primesieve_count_quintuplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime quintuplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve\\_set\\_num\\_threads\(int threads\)](#) to change the number of threads.

#### 8.3.3.4 primesieve\_count\_sextuplets()

```
uint64_t primesieve_count_sextuplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime sextuplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve\\_set\\_num\\_threads\(int threads\)](#) to change the number of threads.

#### 8.3.3.5 primesieve\_count\_triplets()

```
uint64_t primesieve_count_triplets (
    uint64_t start,
    uint64_t stop )
```

Count the prime triplets within the interval [start, stop].

By default all CPU cores are used, use [primesieve\\_set\\_num\\_threads\(int threads\)](#) to change the number of threads.

#### 8.3.3.6 primesieve\_count\_twins()

```
uint64_t primesieve_count_twins (
    uint64_t start,
    uint64_t stop )
```

Count the twin primes within the interval [start, stop].

By default all CPU cores are used, use [primesieve\\_set\\_num\\_threads\(int threads\)](#) to change the number of threads.

#### 8.3.3.7 primesieve\_generate\_n\_primes()

```
void* primesieve_generate_n_primes (
    uint64_t n,
    uint64_t start,
    int type )
```

Get an array with the first n primes  $\geq$  start.

##### Parameters

<i>type</i>	The type of the primes to generate, e.g. INT_PRIMES.
-------------	--

##### Examples:

[store\\_primes\\_in\\_array.c](#).

#### 8.3.3.8 primesieve\_generate\_primes()

```
void* primesieve_generate_primes (
    uint64_t start,
    uint64_t stop,
    size_t * size,
    int type )
```

Get an array with the primes inside the interval [start, stop].

##### Parameters

<i>size</i>	The size of the returned primes array.
<i>type</i>	The type of the primes to generate, e.g. INT_PRIMES.

##### Examples:

[store\\_primes\\_in\\_array.c](#).

**8.3.3.9 primesieve\_get\_max\_stop()**

```
uint64_t primesieve_get_max_stop ( )
```

Returns the largest valid stop number for primesieve.

**Returns**

$2^{64}-1$  (UINT64\_MAX).

**8.3.3.10 primesieve\_nth\_prime()**

```
uint64_t primesieve_nth_prime (
    int64_t n,
    uint64_t start )
```

Find the nth prime.

By default all CPU cores are used, use [primesieve\\_set\\_num\\_threads\(int threads\)](#) to change the number of threads.

**Parameters**

<i>n</i>	if $n = 0$ finds the 1st prime $\geq$ start, if $n > 0$ finds the nth prime $>$ start, if $n < 0$ finds the nth prime $<$ start (backwards).
----------	--

**Examples:**

[nth\\_prime.c](#).

**8.3.3.11 primesieve\_set\_num\_threads()**

```
void primesieve_set_num_threads (
    int num_threads )
```

Set the number of threads for use in [primesieve\\_count\\_\\*](#)() and [primesieve\\_nth\\_prime\(\)](#).

By default all CPU cores are used.

**8.3.3.12 primesieve\_set\_sieve\_size()**

```
void primesieve_set_sieve_size (
    int sieve_size )
```

Set the sieve size in kilobytes.

The best sieving performance is achieved with a sieve size of your CPU's L1 or L2 cache size (per core).

## Parameters

<code>sieve_size</code>	Sieve size in kilobytes.
-------------------------	--------------------------

## Precondition


`sieve_size >= 8 && <= 4096.`

## 8.4 primesieve.hpp File Reference

primesieve C++ API.

```
#include <primesieve/iterator.hpp>
#include <primesieve/primesieve_error.hpp>
#include <primesieve/StorePrimes.hpp>
#include <stdint.h>
#include <vector>
#include <string>
```

Include dependency graph for primesieve.hpp:



## Namespaces

- [primesieve](#)

*Contains primesieve's C++ functions and classes.*

## Macros

- `#define PRIMESIEVE_VERSION "7.0"`
- `#define PRIMESIEVE_VERSION_MAJOR 7`
- `#define PRIMESIEVE_VERSION_MINOR 0`

## Functions

- `template<typename T >`  
`void primesieve::generate_primes (uint64_t stop, std::vector< T > *primes)`  
*Store the primes  $\leq$  stop in the primes vector.*
- `template<typename T >`  
`void primesieve::generate_primes (uint64_t start, uint64_t stop, std::vector< T > *primes)`  
*Store the primes within the interval [start, stop] in the primes vector.*
- `template<typename T >`  
`void primesieve::generate_n_primes (uint64_t n, std::vector< T > *primes)`  
*Store the first n primes in the primes vector.*
- `template<typename T >`  
`void primesieve::generate_n_primes (uint64_t n, uint64_t start, std::vector< T > *primes)`  
*Store the first n primes  $\geq$  start in the primes vector.*
- `uint64_t primesieve::nth_prime (uint64_t n, uint64_t start=0)`  
*Find the nth prime.*
- `uint64_t primesieve::count_primes (uint64_t start, uint64_t stop)`  
*Count the primes within the interval [start, stop].*
- `uint64_t primesieve::count_twins (uint64_t start, uint64_t stop)`  
*Count the twin primes within the interval [start, stop].*
- `uint64_t primesieve::count_triplets (uint64_t start, uint64_t stop)`  
*Count the prime triplets within the interval [start, stop].*
- `uint64_t primesieve::count_quadruplets (uint64_t start, uint64_t stop)`  
*Count the prime quadruplets within the interval [start, stop].*
- `uint64_t primesieve::count_quintuplets (uint64_t start, uint64_t stop)`  
*Count the prime quintuplets within the interval [start, stop].*
- `uint64_t primesieve::count_sextuplets (uint64_t start, uint64_t stop)`  
*Count the prime sextuplets within the interval [start, stop].*
- `void primesieve::print_primes (uint64_t start, uint64_t stop)`  
*Print the primes within the interval [start, stop] to the standard output.*
- `void primesieve::print_twins (uint64_t start, uint64_t stop)`  
*Print the twin primes within the interval [start, stop] to the standard output.*
- `void primesieve::print_triplets (uint64_t start, uint64_t stop)`  
*Print the prime triplets within the interval [start, stop] to the standard output.*
- `void primesieve::print_quadruplets (uint64_t start, uint64_t stop)`  
*Print the prime quadruplets within the interval [start, stop] to the standard output.*
- `void primesieve::print_quintuplets (uint64_t start, uint64_t stop)`  
*Print the prime quintuplets within the interval [start, stop] to the standard output.*
- `void primesieve::print_sextuplets (uint64_t start, uint64_t stop)`  
*Print the prime sextuplets within the interval [start, stop] to the standard output.*
- `uint64_t primesieve::get_max_stop ()`  
*Returns the largest valid stop number for primesieve.*
- `int primesieve::get_sieve_size ()`  
*Get the current set sieve size in kilobytes.*
- `int primesieve::get_num_threads ()`  
*Get the current set number of threads.*
- `void primesieve::set_sieve_size (int sieve_size)`  
*Set the sieve size in kilobytes.*
- `void primesieve::set_num_threads (int num_threads)`  
*Set the number of threads for use in primesieve::count\_\*( ) and primesieve::nth\_prime().*
- `std::string primesieve::primesieve_version ()`  
*Get the primesieve version number, in the form "i.j".*

### 8.4.1 Detailed Description

primesieve C++ API.

primesieve is a library for fast prime number generation, in case an error occurs a [primesieve::primesieve\\_error](#) exception (derived from `std::runtime_error`) is thrown.

Copyright (C) 2018 Kim Walisch, [kim.walisch@gmail.com](mailto:kim.walisch@gmail.com)

This file is distributed under the BSD License.


## 8.5 primesieve\_error.hpp File Reference

The `primesieve_error` class is used for all exceptions within primesieve.


```
#include <stdexcept>
```

```
#include <string>
```

Include dependency graph for `primesieve_error.hpp`:



This graph shows which files directly or indirectly include this file:



### Classes

- class [primesieve::primesieve\\_error](#)

*primesieve* throws a [primesieve\\_error](#) exception if an error occurs e.g.

## Namespaces

- [primesieve](#)

*Contains primesieve's C++ functions and classes.*

### 8.5.1 Detailed Description

The `primesieve_error` class is used for all exceptions within primesieve.

Copyright (C) 2017 Kim Walisch, [kim.walisch@gmail.com](mailto:kim.walisch@gmail.com)

This file is distributed under the BSD License. See the COPYING file in the top level directory.



## Chapter 9

# Example Documentation

### 9.1 count\_primes.c

C program that shows how to count primes.

```
#include <primesieve.h>
#include <inttypes.h>
#include <stdio.h>

int main()
{
    uint64_t count = primesieve_count_primes(0, 1000);
    printf("Primes below 1000 = %" PRIu64 "\n", count);

    return 0;
}
```

### 9.2 count\_primes.cpp

This example shows how to count primes.

```
#include <primesieve.hpp>
#include <stdint.h>
#include <iostream>

int main()
{
    uint64_t count = primesieve::count_primes(0, 1000);
    std::cout << "Primes below 1000 = " << count << std::endl;

    return 0;
}
```

### 9.3 nth\_prime.c

C program that finds the nth prime.

```
#include <primesieve.h>
#include <stdlib.h>
#include <inttypes.h>
#include <stdio.h>

int main(int argc, char** argv)
{
    uint64_t n = 1000;

    if (argc > 1 && argv[1])
        n = atol(argv[1]);

    uint64_t prime = primesieve_nth_prime(n, 0);
    printf("%" PRIu64 "th prime = %" PRIu64 "\n", n, prime);

    return 0;
}
```

## 9.4 nth\_prime.cpp

Find the *nth* prime.

```
#include <primesieve.hpp>
#include <stdint.h>
#include <iostream>
#include <cstdlib>

int main(int, char** argv)
{
    uint64_t n = 1000;

    if (argv[1])
        n = std::atol(argv[1]);

    uint64_t nth_prime = primesieve::nth_prime(n);
    std::cout << n << "th prime = " << nth_prime << std::endl;

    return 0;
}
```

## 9.5 prev\_prime.c

Iterate backwards over primes using [primesieve\\_iterator](#).

```
#include <primesieve.h>
#include <inttypes.h>
#include <stdio.h>

int main()
{
    primesieve_iterator it;
    primesieve_init(&it);

    /* primesieve_skipto(&it, start_number, stop_hint) */
    primesieve_skipto(&it, 2000, 1000);
    uint64_t prime;

    /* iterate over primes from 2000 to 1000 */
    while ((prime = primesieve_prev_prime(&it)) >= 1000)
        printf("%" PRIu64 "\n", prime);

    primesieve_free_iterator(&it);

    return 0;
}
```

## 9.6 prev\_prime.cpp

Iterate backwards over primes using `primesieve::iterator`.

```
#include <primesieve.hpp>
#include <iostream>

int main()
{
    primesieve::iterator it;
    it.skipto(2000);
    uint64_t prime = it.prev_prime();

    // iterate over primes from 2000 to 1000
    for (; prime >= 1000; prime = it.prev_prime())
        std::cout << prime << std::endl;

    return 0;
}
```

## 9.7 primesieve\_iterator.c

Iterate over primes using C `primesieve_iterator`.

```
#include <primesieve.h>
#include <inttypes.h>
#include <stdio.h>

int main()
{
    primesieve_iterator it;
    primesieve_init(&it);

    uint64_t sum = 0;
    uint64_t prime = 0;

    /* iterate over the primes below 10^9 */
    while ((prime = primesieve_next_prime(&it)) < 1000000000ull)
        sum += prime;

    printf("Sum of the primes below 10^9 = %" PRIu64 "\n", sum);

    /* generate primes > 1000 */
    primesieve_skipto(&it, 1000, 1100);

    while ((prime = primesieve_next_prime(&it)) < 1100)
        printf("%" PRIu64 "\n", prime);

    primesieve_free_iterator(&it);

    return 0;
}
```

## 9.8 primesieve\_iterator.cpp

Iterate over primes using `primesieve::iterator`.

```
#include <primesieve.hpp>
#include <iostream>

int main()
{
    primesieve::iterator it;
    uint64_t prime = it.next_prime();
    uint64_t sum = 0;
```

```

// iterate over the primes below 10^9
for (; prime < 1000000000ull; prime = it.next_prime())
    sum += prime;

std::cout << "Sum of the primes below 10^9 = " << sum << std::endl;

// generate primes > 1000
it.skipto(1000);
prime = it.next_prime();

for (; prime < 1100; prime = it.next_prime())
    std::cout << prime << std::endl;

return 0;
}

```

## 9.9 store\_primes\_in\_array.c

Store primes in a C array.

```

#include <primesieve.h>
#include <stdio.h>

int main()
{
    uint64_t start = 0;
    uint64_t stop = 1000;
    size_t i;
    size_t size;

    /* store the primes below 1000 */
    int* primes = (int*) primesieve_generate_primes(start, stop, &size,
        INT_PRIMES);

    for (i = 0; i < size; i++)
        printf("%i\n", primes[i]);

    primesieve_free(primes);
    uint64_t n = 1000;

    /* store the first 1000 primes */
    primes = (int*) primesieve_generate_n_primes(n, start,
        INT_PRIMES);

    for (i = 0; i < n; i++)
        printf("%i\n", primes[i]);

    primesieve_free(primes);
    return 0;
}

```

## 9.10 store\_primes\_in\_vector.cpp

Store primes in a `std::vector` using `primesieve`.

```

#include <primesieve.hpp>
#include <vector>

int main()
{
    std::vector<int> primes;

    // Store primes <= 1000
    primesieve::generate_primes(1000, &primes);

    primes.clear();

    // Store primes inside [1000, 2000]
    primesieve::generate_primes(1000, 2000, &primes);
}

```

```
primes.clear();

// Store first 1000 primes
primesieve::generate_n_primes(1000, &primes);

primes.clear();

// Store first 10 primes >= 1000
primesieve::generate_n_primes(10, 1000, &primes);

return 0;
}
```



# Index

- count\_primes
  - primesieve, 12
- count\_quadruplets
  - primesieve, 12
- count\_quintuplets
  - primesieve, 13
- count\_sextuplets
  - primesieve, 13
- count\_triplets
  - primesieve, 13
- count\_twins
  - primesieve, 13
- get\_max\_stop
  - primesieve, 13
- iterator
  - primesieve::iterator, 17
- iterator.h, 21
  - primesieve\_next\_prime, 22
  - primesieve\_prev\_prime, 22
  - primesieve\_skipto, 23
- iterator.hpp, 23
- next\_prime
  - primesieve::iterator, 18
- nth\_prime
  - primesieve, 14
- prev\_prime
  - primesieve::iterator, 18
- primesieve, 11
  - count\_primes, 12
  - count\_quadruplets, 12
  - count\_quintuplets, 13
  - count\_sextuplets, 13
  - count\_triplets, 13
  - count\_twins, 13
  - get\_max\_stop, 13
  - nth\_prime, 14
  - set\_num\_threads, 14
  - set\_sieve\_size, 14
- primesieve.h, 25
  - primesieve\_count\_primes, 27
  - primesieve\_count\_quadruplets, 28
  - primesieve\_count\_quintuplets, 28
  - primesieve\_count\_sextuplets, 28
  - primesieve\_count\_triplets, 28
  - primesieve\_count\_twins, 28
  - primesieve\_generate\_n\_primes, 29
  - primesieve\_generate\_primes, 29
  - primesieve\_get\_max\_stop, 29
  - primesieve\_nth\_prime, 30
  - primesieve\_set\_num\_threads, 30
  - primesieve\_set\_sieve\_size, 30
- primesieve.hpp, 31
- primesieve::iterator, 17
  - iterator, 17
  - next\_prime, 18
  - prev\_prime, 18
  - skipto, 18
- primesieve::primesieve\_error, 19
- primesieve\_count\_primes
  - primesieve.h, 27
- primesieve\_count\_quadruplets
  - primesieve.h, 28
- primesieve\_count\_quintuplets
  - primesieve.h, 28
- primesieve\_count\_sextuplets
  - primesieve.h, 28
- primesieve\_count\_triplets
  - primesieve.h, 28
- primesieve\_count\_twins
  - primesieve.h, 28
- primesieve\_error.hpp, 33
- primesieve\_generate\_n\_primes
  - primesieve.h, 29
- primesieve\_generate\_primes
  - primesieve.h, 29
- primesieve\_get\_max\_stop
  - primesieve.h, 29
- primesieve\_iterator, 20
- primesieve\_next\_prime
  - iterator.h, 22
- primesieve\_nth\_prime
  - primesieve.h, 30
- primesieve\_prev\_prime
  - iterator.h, 22
- primesieve\_set\_num\_threads
  - primesieve.h, 30
- primesieve\_set\_sieve\_size
  - primesieve.h, 30
- primesieve\_skipto
  - iterator.h, 23
- set\_num\_threads
  - primesieve, 14
- set\_sieve\_size
  - primesieve, 14
- skipto

primesieve::iterator, [18](#)